

## Instructions

Unplug the BearExtender USB cable first.

- 1. Run "Remove workaround" then restart
- 2. Run "Remove old files" then restart
- 3. Run "Install 5.4" do not restart yet
- 4. When "Install 5.4" finishes, plug in the BearExtender USB cable.
- 5. Now click restart.

## After the third restart:

- 6. Look for the dot signal icon in your menu bar near the clock
- 7. When the BearExtender window opens click your network once, then click "Add to favorites"
- 8. Enter your Wi-Fi network password if required
- 9. Now you will be taken to the Favorites tab.
- 10. Select the network you just added and click "Activate".

From now on, BearExtender will automatically connect within 7-10 seconds the next time you unplug/plug in the USB cable or sleep/wake/shutdown/startup your Mac.

## Additional notes

You can now unplug the USB cable at any time when finished using BearExtender. You do not need to shutdown first.

Please report issues to support@bearextender.com